


Configuring SmarterU for Single Sign-On

Configuring SmarterU for SSO enables administrators to manage their users using Citrix Gateway service. Users can securely log on to SmarterU using their enterprise credentials.


To configure SmarterU for SSO through SAML, follow the steps below:

1. In a browser, type the URL, <http://<companyname>.smarteru.com/remote-login/login.cfm> and press **Enter**.
2. Type the credentials and click **Login**.



The screenshot shows the SmarterU login interface. At the top, there is a logo consisting of three blue circles followed by the text "SmarterU" in a bold, sans-serif font, with "TRAIN • LEARN • RETAIN" in smaller letters below it. Below the logo is a light gray form area with two input fields: "Email:" and "Password:", each with a corresponding input box. Underneath these fields is a dark blue "Login" button with white text. Below the "Login" button is a link "forgot password". At the bottom left, there is a copyright notice: "LMS © 2018 Neovation Corporation All Rights Reserved". At the bottom right, it says "powered by" next to the SmarterU logo.


3. On the Home page, under Account Admin, click **Account Settings**.



4. In the Account Profile page, click **External Authorization**.

Account Profile		<input checked="" type="checkbox"/> Save	<input type="button" value="Cancel"/>
<div style="display: flex; justify-content: space-between;"> <div style="flex-grow: 1;"> <ul style="list-style-type: none"> General Information Settings Customization Custom Menu Items Quick User Add Email Options Email Template Options Post-Course Evaluations Account Message Contact Information Custom User Fields Custom Organization Fields Customize Grid Columns Webinar Providers Portals External Authorization (highlighted in blue) </div> <div style="text-align: right;"> <input checked="" type="checkbox"/> Enable External Authorization </div> </div>			
Master Login Control: <input type="radio"/> SmarterU <input type="radio"/> External Authorization <input type="radio"/> Both <input type="radio"/> User-Specified		User Default Login: <input type="radio"/> SmarterU <input type="radio"/> External Authorization <input type="radio"/> Both	

5. In the External Authorization section, specify the following details:



- i. **Enable External Authorization:** Select to enable authorization.
- ii. **Master Login:** Select **Both**.
- iii. **User Default Login:** Select **Both**.
- iv. **Login URL:** Enter the IdP URL, SAML 2.0 endpoint, for example, <https://example.com/saml/login>
- v. **Customize Login Button Text:** Enter the text for Login button. This is used to log in with SSO.
- vi. **Customize Portal Login Button Text:** Enter the text for Portal Login button. This is used to log in to the default application.
- vii. **Enable SAML:** Select to enable SAML 2.0.
- viii. **IDP Metadata:** Enter the IDP metadata.
- ix. **Identifier Attribute/Claim:** From the drop-down list, select **Name ID**.
- x. **Identifier Type:** Click **Email**.

The SAML configuration is saved.